

[Dialer Defaults]

Init1 = ATZ
Init2 = ATQ0 V1 E1 S0=0 &C1 &D2 +FCLASS=0
Modem Type = Analog Modem
Baud = 9600
New PPPD = yes
Modem = /dev/ttyUSB0
ISDN = 0
; Phone = <Target Phone Number>
; Password = <Your Password>
; Username = <Your Login Name>

[Dialer AT_n_T_3G]

Init1 = ATZ
Init2 = ATQ0 V1 E1 S0=0 &C1 &D2 +FCLASS=0
Init3 = AT+CGDCONT=1,"IP","wap.cingular",,0,0
Modem Type = USB Modem
Phone = *99***1#
Username = wap@cingulargprs.com
Password = CINGULAR1
Modem = /dev/ttyUSB0
Stupid Mode = 1
ISDN = 0
Dial Command = ATDT

[Dialer TMO_2G]

Modem Type = Analog Modem
Phone = *99#
ISDN = 0
Baud = 115200
Username = user
Password = pass
Modem = /dev/ttyO1
Init1 = ATZ
Init2 = ATQ0 V1 E1 S0=0 &C1 &D2 +FCLASS=0
Init3 = at+cgdcont=1,"IP","epc.tmobile.com"
Stupid Mode = 1
New PPPD = yes

[Dialer Vodafone_3G]

Init1 = ATZ
Init2 = ATQ0 V1 E1 S0=0 &C1 &D2 +FCLASS=0
Modem Type = Analog Modem
Baud = 9600
New PPPD = yes
Modem = /dev/ttyUSB0
ISDN = 0
Phone = *99#
Password = 0
Username = 0

[Dialer Vodafone_2G]

Init1 = ATZ

Init2 = ATQ0 V1 E1 S0=0 &C1 &D2 +FCLASS=0

Modem Type = Analog Modem

Baud = 9600

New PPPD = yes

Modem = /dev/ttyO1

ISDN = 0

Phone = *99#

Password = 0

Username = 0

[Dialer Airtel_3G]

Init1 = ATZ

Init2 = ATQ0 V1 E1 S0=0 &C1 &D2 +FCLASS=0

Modem Type = Analog Modem

Baud = 9600

New PPPD = yes

Modem = /dev/ttyUSB0

ISDN = 0

Phone = *99#

Password = airtel

Username = airtel

[Dialer Airtel_2G]

Init1 = ATZ

Init2 = ATQ0 V1 E1 S0=0 &C1 &D2 +FCLASS=0

Modem Type = Analog Modem

Baud = 9600

New PPPD = yes

Modem = /dev/ttyO1

ISDN = 0

Phone = *99#

Password = airtel

Username = airtel